# **Guide: Setting Up Samba on Ubuntu for Windows Access**

# **Prerequisites**

- Ubuntu Server with sudo access.
- Windows Client to access the shared folder.
- Basic knowledge of Linux commands.

# Step 1: Install and Configure Samba on Ubuntu

### **Update and Install Samba**:

```
sudo apt update
sudo apt install samba -y
```

**Create a Shared Directory**: Choose or create a directory to share. Here, we'll use /home/ubuntu/shared\_data:

```
sudo mkdir -p /home/ubuntu/shared_data
```

**Set Directory Permissions**: To allow Samba to access this directory, give read, write, and execute permissions to the ubuntu user:

```
sudo chown -R ubuntu:ubuntu /home/ubuntu/shared_data
sudo chmod -R 755 /home/ubuntu/shared_data
```

### Edit Samba Configuration: Open the Samba configuration file:

sudo nano /etc/samba/smb.conf Add the following at the end of the file:

```
[shared_data]
path = /home/ubuntu/shared_data
available = yes
valid users = ubuntu
read only = no
browsable = yes
public = yes
writable = yes
force user = ubuntu
```

#### Save and Exit:

- Press CTRL + 0, press Enter to save.
- Press CTRL + X to exit.

**Create a Samba User**: Add the Linux user to Samba and set a password:

```
sudo smbpasswd -a ubuntu
```

**Restart Samba Service**: To apply changes:

```
sudo systemctl restart smbd
```

# **Step 2: Set Permissions on the Shared Directory**

Make sure that files in the directory are readable by the Samba service:

#### **Set Permissions for Files:**

```
sudo chmod -R 755 /home/ubuntu/shared_data
sudo chmod -R o+r /home/ubuntu/shared_data/*
```

# Step 3: Access the Shared Folder from Windows

### 1. Check Windows Firewall and Network Discovery

- Enable Network Discovery:
- Go to Control Panel > Network and Sharing Center > Advanced sharing settings.
- o Ensure Network Discovery is enabled.
- Allow File Sharing in Windows Firewall:
- o Open Windows Defender Firewall.
- Click on Allow an app or feature through Windows Defender Firewall.
- Make sure File and Printer Sharing is checked for the network you're connected to.

### 2. Map the Network Drive in Windows:

- Open File Explorer.
- Right-click on This PC and select Map network drive.
- 3. Enter Path and Credentials:
  - Folder: Enter the path in the format \\<Ubuntu\_IP\_Address>\shared\_data
     (replace <Ubuntu\_IP\_Address> with your actual Ubuntu server IP).
  - $\circ$  OR

net use Z: \\172.31.34.36\shared\_data /user:your\_username <your\_password>

Check Connect using different credentials.

Click Finish.

### 4. Authenticate:

- Enter the Samba username and password you set earlier (ubuntu and its password).
- Check **Remember my credentials** and click **OK**.

# 5. Access the Drive:

o Your shared folder should now be accessible as a network drive in Windows.